



## Mozilla Thunderbird

Once you have downloaded and installed Thunderbird on to your machine, you can follow these steps to set up your pair email:

1. Open the Thunderbird application
2. On the main page, under the **Set up an account** heading, click **Email**



This page will come up automatically for new users and some existing users. If this page does not come up default, you can click **Local Folders** in the left sidebar to navigate to the page.



3. A window will appear. Enter your email information here:

✕

**Set Up an Existing Email Account**

Your name:  Your name, as shown to others

Email address:  Your existing email address


Password:

Remember password

<b>Your Name</b>	This name will appear as the sender of your email
<b>Email Address</b>	The pair email address you are planning to use with Thunderbird
<b>Password</b>	Your email address' password.

4. Click **Continue**

5. Select **IMAP** or **POP**. **IMAP** is recommended.



Set Up an Existing Email Account

Your name:  Your name, as shown to others

Email address:  Your existing email address

Password:

Remember password

Configuration found by trying common server names


IMAP (remote folders)  POP3 (keep mail on your computer)

Incoming: IMAP, mail.poof.pairsite.com, STARTTLS

Outgoing: SMTP, mail.poof.pairsite.com, STARTTLS

Username:

6. Click **Manual Config**



Set Up an Existing Email Account

Your name:  Your name, as shown to others

Email address:  Your existing email address

Password:

Remember password

Configuration found by trying common server names

IMAP (remote folders)  POP3 (keep mail on your computer)

Incoming: IMAP, mail.poof.pairsite.com, STARTTLS

Outgoing: SMTP, mail.poof.pairsite.com, STARTTLS

Username:

Enter the incoming and outgoing mail servers and the username: Mail serves should be set as follows

<b>Incoming</b>	Incoming mail server <b>mail.hamiltoncom.net</b> or <b>mail.futiva.net</b>
<b>Outgoing</b>	Outgoing mail server <b>mail.hamiltoncom.net</b> or <b>mail.futiva.net</b>
<b>Username</b>	The email address you are currently setting up

7. Enter/verify ports for incoming and outgoing servers.

<b>Incoming</b>	For IMAP port should be 933 For POP3 port should be 95
<b>Outgoing</b>	Outgoing port should be 587

8. Set SSL for incoming and outgoing servers.

<b>Incoming</b>	Set to SSL/TLS by clicking drop down arrow
<b>Outgoing</b>	Set to STARTTLS by clicking drop down arrow

9. Verify authentication is set to Normal Password for both incoming and outgoing.

10. Verify username is the full email address for both incoming and outgoing.

11. Click Done